




EjsS Tracker Elements

Sending EjsS data to Tracker



- *In EjsS: Tracker element*
- *In Tracker: data track (automatic)*

Useful resources:


[Tracker Help: data track](#)

EjsS example: Ball Toss with Tracker



EjsS Tracker Elements

Create Tracker Element in EjsS



- *Model Elements page*
- *External models*
- *Drag icon to create element*
- *Assign a name to the element—in this case "ball"*



EjsS Tracker Elements

Enter a name for the data track

Editor for model element ball (Tracker) [X]


Name:	"ball"			[Link]	
Video File:		[Folder]	[Link]		
TRK File:		[Folder]	[Link]		
Start Frame:		[Link]	Step Size:		[Link]
End Frame:		[Link]	Use Data Time:		[Link]
t:		[Link]	x:		[Link]
		[Link]	y:		[Link]

- *Dbl-click the element to open property editor*
- *Name must be in quotes—here "ball"*
- *Name is assigned to the data track in Tracker*
- *Name may be same as element name*
- *Other properties will be set later*



EjsS Tracker Elements

Append initial data to element




- *Click to add new page in Initialization if needed*
- *Call method `append(t, x, y)` on element "ball"*



EjsS Tracker Elements

Append data to element after ODE step




*Right-click to add new page in Model/Evolution
Call method `append(t, x, y)` on element "ball"*



EjsS Tracker Elements

Add button to connect to Tracker




- *Create button in View page by dragging to a panel*
- *Dbl-click button to open property editor*
- *Button Text must be in quotes*
- *Button Action is connect() method*
- *Call connect() method on element "ball"*



EjsS Tracker Elements

Initial testing




- *Connect button should create a data track in Tracker*
- *Step forward button should append data*
- *Play button should append more data*
- *Reset button should reset data track*



EjsS Tracker Elements

Data track settings



- *Video start frame*
- *Frame count*
- *Data start index*
- *Data stride*
- *Time basis*
- *Set in model builder*



EjsS Tracker Elements

Comparing data tracks with videos

- Video*
- *Calibrate scale*
 - *Set origin, adjust angle*
 - *Set clip start to first frame of interest*
 - *Set frame rate or frame dt*
 - *Set other clip properties if desired*

- Track*
- *Set properties in model builder*



EjsS Tracker Elements

Saving video settings in TRK file

- *Delete the data track before saving*
- *Save TRK file with same or similar name to EjsS model/element*
- *Undo in Tracker to restore data track if desired*



EjsS Tracker Elements

Using TRK and video in EjsS tracker element

Editor for model element ball (Tracker) [X]


Name:	"ball"		[Link]					
Video File:		[Folder Icon]	[Link]					
TRK File:	"./BallToss/BallTossSetUp.trk"		[Folder Icon] [Link]					
Start Frame:	9	[Link]	Step Size:		[Link]			
End Frame:	30	[Link]	Use Data Time:		[Link]			
t:		[Link]	x:		[Link]	y:		[Link]

- Copy both TRK file and video to EjsS source folder
- Check that copied TRK opens video
- Open tracker element in EjsS
- Use "open" button to set TRK file path
- Copy data track settings to EjsS element
- No need to enter video file path when using TRK



EjsS Tracker Elements

Final testing



- *Connect button should open the calibrated video and create the data track*
- *Other buttons as before*